System Parameters RP

General

For basic information on using system parameters, see the System Parameters chapter[1] in the manual for the "Portal & Organization" module.

The parameters of the RP module apply system-wide; there are no client settings that override them.

Reference of the Relevant System Parameters for the RP Module

Module	Bean	Property	Explanation	Possible value(s)
rp	RpReportDefinitionService	showDeleteAllButLastButton	When editing a report definition, shows the button used to delete all report designs except the latest.	true/false (default: true)
rp	RpReportDefinitionService	showDeleteButton	When editing a report definition, shows the button used to delete the latest report design.	true/false (default: true)
rp	RpReportDefinitionService	showDownloadButton	When editing a report definition, shows the button for downloading the report design.	true/false (default: true)
rp	RpOptions	maxLogSizeMegabyte	Maximum size in MB up to which the BIRT log of a report execution is displayed; longer logs are truncated.	Number (default: 10)
rp	RpOptions	maxReportExecutionTimeSecond	Defines the maximum time in seconds that BIRT report generation may take. If this value is exceeded at runtime, generation is aborted. Applies only to HTML output (not to PDF and Excel); 0 means no limit.	default: 45
rp	RpOptions	maxReportSizeMegabyte	Defines the maximum size in MB of the report generated by BIRT. Applies only to	default: 7

			HTML output (not to PDF and Excel); 0 means no limit.	
rp	RpOptions	selectedUidsPartitionSize	Maximum number of selected records (e.g., persons) that are queried together in a database query of a report; larger selections are split into multiple queries. The value must suit the database (Oracle at most approx. 500, SQL Server at most approx. 2100).	Number (default: 2000)
rp	BirtEngineFactory	logLevel	Logging level of the BIRT engine (Java log level, e.g., WARNING, INFO, FINE). Evaluated at startup or when the BIRT engine is reinstalled.	Log level (default: WARNING)
rp	BirtEngineFactory	logDir	Directory for the log files of the BIRT engine. If the parameter is empty, the directory birtengine/log in the Webdesk working directory is used. Evaluated at startup or when the BIRT engine is reinstalled; the log files are deleted in the process.	Path (default: empty)

1. /daisy/personalwolke-admin/5122-dsy.html?language=4