Loose Groups

Under **Loose groups** you can define the affiliation to several non-hierarchical groups. The number of loose groups to which the employee can be assigned is unlimited.

WARNUNG

Note: The user must always be assigned to the loose group xx-ALLE - otherwise no menu tree is available after login!

e Gruppen PP ~				
with History				
sw duonb	Valid from		Valid till	
elect an Option	•	m		
4		Valid till		Delete
92-Admin (Alle Administratoren) 92-ALLE (Alle Mitarbeiter PW Prof)	100	01/01/3000	m	
e-ALLE (alle Mitarbeiter FW Prof) 9-KloskAdmin (PP-KloskAdmin)	100	01/01/3000	m	
	100	01/01/3000	m	
9P-Management (Alle Manager)	m	01/01/3000	m	
20-Mitarbeiter (Mitarbeiter Landwirtschaft)				

(This screenshot shows the 3 standard loose groups. The new user must be assigned at least to the group xx-ALLE (PB-ALLE).)

WARNUNG

In order to offer the user **additional rights** (also in the Project-Time and Travel modules), he must also be added to one of the following loose groups!

Personalwolke Time:

PB-ALLE	PB-ALLE + PB-Management	PB-ALLE + PB-Admin
Standard-Group - every user MUST be assigned to this group!	Management-Group - users who are added to this group receive additional menu items for the evaluation of company employees - Konten Auswertung ¹ , Kalenderübersicht ² , Jahreskalender ³ und Statistik ⁴ .	Administrator-Group -Users added to this group get additional menu items for managing the Organigramms ⁵ , Personen ⁶ peop and Rollen ⁸ roles, as well as the ability to Benutzer umschalten ⁹ switch users to view the webdesk from the perspective of the selected user.

Of course it is also possible to add a user to all loose groups and thus unlock the administration AND management menu items to the user or a simple standard user is created which is only added to the loose group PB-ALLE.

WARNUNG

The menu item Time management --> Correction client represents a special case. Only persons who have assigned the Personnel role can use this correction client (regardless of the loose groups to which they have been added) to change bookings. In some cases users can also use correction client for tracking time.

Personalwolke Travel

If you are a user of the "Travel" module, the following loose groups are also available for managing user rights:

PB-TM-User	PB-TM-Manager	PB-TM-Admin
 Apply for / account for trip (depending on the definition according to the furnishing workshop) Info / My travels 	Management / Travel of my employees	 Administration / Travel Expenses / All Trips Management / Travel of my employees

Personalwolke Project-Time

If you are a user of the "Project Time" module, the following loose groups are also available for managing user rights:

PB-PTM-Usr	PB-PTM-Mgm	PB-PTM-ProjMngr	PB-PTM-Admin
 Project time booking Enter project time Info / My project times 	 Enter project time Management / project times of my employees 	Management / Project expenses	 Enter project time Administration / Project time / Projects Management / project times of my employees

How to add user to a group

We select the **PB-ALLE** group and click Save. This assigns the employee to the loose group **PB-ALLE**.

ettings Groups Roles Action Pe	rmissions In competence of roleholders Cac	he Login Attempts NFC	ags Modules				
ose Gruppen PP -							
	with History						
New group				Valid from		Valid till	
Select an Option				•	m		
	Name		Valid from		Valid till		Delete
Orgstructure	Hume						
	PP-KioskAdmin (PP-KioskA	dmin)	28/01/2020		01/01/3000	<u></u>	U
Lose Gruppen PP			28/01/2020 06/06/2013		01/01/3000	<u></u>	_
Drgstructure Solution Composition PP Solution Composition PP Solution Composition PP	PP-KioskAdmin (PP-KioskA	oren)					

In summary, it can be said that when creating a new person regarding the groups / roles, the following things must be considered:

- Person has been assigned to exactly one hierarchical group.
- Person has been assigned to the loose group PB-ALLE.
 - Person gets optional additional rights by adding to loose groups
 - PB management and / or PB admin (when using the time module)
 - PB-TM user / PB-TM manager / PB-TM admin (when using the travel module)
 - PB-PTM-User / PB-PTM-Mgm / PB-PTM-ProjMngr / PB-PTM-Admin (when using the project time module)
- Person gets optional additional rights (correction client) by adding the role Personnel

Role assignment for managers and personnel is explained in the next section.

Tab: Roles

Under **Roles**, you can find an overview of the roles assigned to this person in the company. The following screenshot shows that the person has not yet been assigned a role.

Settings	Groups	Roles Action Permissions In cor	npetence of roleholde	rs Cache	Login At	tempts	NFC Tags	Modules	
			with	History 🗌					
+ New	v Role Ass	gnment							
									Entries 1 - 3 of 3 \parallel \ll $<$ 1 \checkmark $>$ \gg Lines: 5
Name		Competence target	inherited from	Valid from		Valid till		Ranking	Delete / Edit
🎄 Perso	onal	PersonalWolke Prof		10/06/2013	m	01/01/300	00	1	ê 🖌
PersoVorge		PersonalWolke Prof)H)	10/06/2013 19/01/2016		01/01/300 01/01/300		1	

If the employee is now to be assigned another role (superior, personnel), this is done by clicking on the **New Role Holder** button.

ettings	Groups	Roles	Action Permissions	In competence of roleholders	Cache	Login Attempts	NFC Tags Modules				
				with Hist	tory 🗌						
New Ro	ole Assignm	nent									C
New R	oleholder			Competence target		Valid from		Valid till		Ranking	
									m	1.	

• New role assignment Selection of the role

personnel) to be assigned to the employee.

- Competence target refers to the person/group for which the employee is to be responsible.
- Valid from / Valid to describes the period in which the employee is assigned the selected role.
- The **order** determines the deputy (sequence 1 = superior, 2 = deputy, 3,4 = if several persons are defined as deputies, the system determines who receives an application for processing).

Example: New role assignment "superior", competence objective: group, "PB-ENTW (development)" - this means that the person performs the role of superior for the group PB-ENTW, i.e. all applications submitted by a person from the group PB-ENTW and requiring approval / review by the role of superior end up with this person. Of course, a special person could also be appointed instead of the group. In this case, the Superior role only applies to the person who was defined.

A person can be assigned several roles with different competence goals!

ettings Groups Role	es Action Permissions	In competence of roleholders	Cache Login A	Attempts NFC Tags	Modules				
		with Hist	ory						
New Role Assignment									•
New Roleholder		Competence target	Vali	id from		Valid till		Ranking	
		[~		m			1	

A click on Save defines that the employee is now the manager of the PB-ENTW (Development) group.

(manag

- 1. /daisy/personalwolke-admin/6024-dsy.html?language=4
- 2. /daisy/personalwolke-admin/6025-dsy.html?language=4
- 3. /daisy/personalwolke-admin/6026-dsy.html?language=4
- 4. /daisy/personalwolke-admin/6027-dsy.html?language=4
- 5. /daisy/personalwolke-admin/5881-dsy.html?language=4
- 6. /daisy/personalwolke-admin/5885-dsy.html?language=4
- 7. /daisy/personalwolke-admin/5884-dsy.html?language=4
- 8. /daisy/personalwolke-admin/5886-dsy.html?language=4
- 9. /daisy/personalwolke-admin/5887-dsy.html?language=4