Loose Groups

Under **Loose groups** you can define the affiliation to several non-hierarchical groups. The number of loose groups to which the employee can be assigned is unlimited.

WARNUNG

Note: The user must always be assigned to the loose group xx-ALLE - otherwise no menu tree is available after login!

is Groups Roles Action Permissions In competence of roleholders Cache Login Attempts NFC Tags Modules				
with History				
New group	Valid from		Valid till	
Select an Option	*	m		
		Valid till		Delete
		01/01/3000	Ó	
		01/01/3000		
		01/01/3000	m	
		01/01/3000	m	
DD Mitachaltar (Mitachaltar Landwictashaft)				
PP-Mitarbeiter (Mitarbeiter Landwirtschaft) PP-Travel (PP-Travel)				

(This screenshot shows the 3 standard loose groups. The new user must be assigned at least to the group xx-ALLE (PB-ALLE).)

WARNUNG

In order to offer the user **additional rights** (also in the Project-Time and Travel modules), he must also be added to one of the following loose groups!

Personalwolke Time:

Of course it is also possible to add a user to all loose groups and thus unlock the administration AND management menu items to the user or a simple standard user is created which is only added to the loose group PB-ALLE.

WARNUNG

The menu item Time management --> Correction client represents a special case. Only persons who have assigned the Personnel role can use this correction client (regardless of the loose groups to which they have been added) to change bookings.

Personalwolke Travel

If you are a user of the "Travel" module, the following loose groups are also available for managing user rights:

PB-TM-User	PB-TM-Manager	PB-TM-Admin
 Apply for / account for trip (depending on the definition according to the furnishing workshop) Info / My travels 	Management / Travel of my employees	 Administration / Travel Expenses / All Trips Management / Travel of my employees

Personalwolke Project-Time

If you are a user of the "Project Time" module, the following loose groups are also available for managing user rights:

PB-PTM-Usr	PB-PTM-Mgm	PB-PTM-ProjMngr	PB-PTM-Admin
 Project time booking Enter project time Info / My project times 	 Enter project time Management / project times of my employees 	Management / Project expenses	 Enter project time Administration / Project time / Projects Management / project times of my employees

We select the **PB-ALLE** group and click Save. This assigns the employee to the loose group **PB-ALLE**.

In summary, it can be said that when creating a new person regarding the groups / roles, the following things must be considered:

- Person has been assigned to exactly one hierarchical group.
- Person has been assigned to the loose group PB-ALLE.
- Person gets optional additional rights by adding to loose groups
 - PB management and / or PB admin (when using the time module)
 - PB-TM user / PB-TM manager / PB-TM admin (when using the travel module)
 - PB-PTM-User / PB-PTM-Mgm / PB-PTM-ProjMngr / PB-PTM-Admin (when using the project time module)
- Person gets optional additional rights (correction client) by adding the role Personnel

Role assignment for managers and personnel is explained in the next section.

Tab: Roles

Under **Roles**, you can find an overview of the roles assigned to this person in the company. The following screenshot shows that the person has not yet been assigned a role.

Einstellungen Grup	ppen Rollen Aktio	nsberechtigungen	Im Kompetenzl	bereich dieser Ro	lleninhaber	Module
mit Vergangenheit						
Neuer Rollenin	haber					
			Einträge	1 - 1 von 1 🗰	1 🔻 🚳 🏓	▶ <u>5</u> ▼
Name	Kompetenzziel	vererbt von	Gültig von	Gültig bis	Reihung	Löschen / Bearbeiten

If the employee is now to be assigned another role (superior, personnel), this is done by clicking on the **New Role Holder** button.

Einstellungen Gruppen	Rollen Ak	tionsberechtigungen	Im Kompetenzbere	ich dieser Rolleninhaber	Module
mit Vergangenheit					
Neuer Rolleninhaber					8
Neuer Rolleninhaber		Kompetenzziel	Gültig von	Gültig bis	Reihung
		•			1

• New role assignment Selection of the role

personnel) to be assigned to the employee.

- Competence target refers to the person/group for which the employee is to be responsible.
- Valid from / Valid to describes the period in which the employee is assigned the selected role.
- The **order** determines the deputy (sequence 1 = superior, 2 = deputy, 3,4 = if several persons are defined as deputies, the system determines who receives an application for processing).

Example: New role assignment "superior", competence objective: group, "PB-ENTW (development)" - this means that the person performs the role of superior for the group PB-ENTW, i.e. all applications submitted by a person from the group PB-ENTW and requiring approval / review by the role of superior end up with this person. Of course, a special person could also be appointed instead of the group. In this case, the Superior role only applies to the person who was defined.

A person can be assigned several roles with different competence goals!

A click on Save defines that the employee is now the manager of the PB-ENTW (Development) group.

The assigned roles can also be withdrawn / changed from the user by means of Delete Edit

- $1. \ /daisy/personal wolke-default-en/Time-Base/10313-dsy/ta_getOrgJournal \$Base.cact.html$
- $2. \ /daisy/personal wolke-default-en/Time-Base/10313-dsy/ta_getOrgCalendar \$ Base.cact.html$
- $3. \ /daisy/personal wolke-default-en/Time-Base/10313-dsy/ta_getOrgCalendarYearly \$Base.cact.html$
- $4. \ /daisy/personal wolke-default-en/Time-Base/10313-dsy/ta_getStatistic \$Base.cact.html$
- $5. \ /daisy/personal wolke-default-en/Time-Base/10473-dsy/po_orgBuilder.act.html$
- 6. /daisy/personalwolke-default-en/Time-Base/10473-dsy/5885-dsy.html
- 7. /daisy/personalwolke-default-en/Time-Base/10473-dsy/Groups.html
- $8. \ /daisy/personal wolke-default-en/Time-Base/10473-dsy/po_showRoles.act.html$
- 9. /daisy/personalwolke-default-en/6124-dsy/5887-dsy.html