Loose Groups

Under **Loose groups** you can define the affiliation to several non-hierarchical groups. The number of loose groups to which the employee can be assigned is unlimited.

WARNUNG

Note: The user must always be assigned to the loose group xx-ALLE - otherwise no menu tree is available after login!

tings Groups	s Roles	Action Permissions	In competence of roleholders	Cache	Login Attempts	NFC Tags	Modules				G
ose Gru	uppen F	•Р ~									
			with His	tory 🗌							
New group								Valid from		Valid till	
Select an Op	ption						×		8		
pro belevie ((Alle Administ	ratoren)							Valid till		Delete
	(Alle Autilition	(acoren)							01/01/3000	8	
-	Alle Mitarbeite	r PW Prof)							01/01/3000		
PP-ALLE (A PP-KioskAd	Alle Mitarbeite dmin (PP-Kios								01/01/3000		
PP-ALLE (A PP-KioskAd PP-Manage	dmin (PP-Kios	kAdmin)						40		11 11 11	
 PP-ALLE (A) PP-KioskAd PP-Manage 	dmin (PP-Kios ement (Alle Ma	kAdmin)							01/01/3000		
 PP-ALLE (A) PP-KioskAd PP-Manage 	dmin (PP-Kios ement (Alle Ma eiter (Mitarbeit	kAdmin) anager)							01/01/3000 01/01/3000	11 11 11	

(This screenshot shows the 3 standard loose groups. The new user must be assigned at least to the group xx-ALLE (PP-ALLE).)

WARNUNG

In order to offer the user **additional rights** (also in the Project-Time and Travel modules), he must also be added to one of the following loose groups!

Personalwolk	e Time:
--------------	---------

PP-ALLE	PP-ALLE + PP-Management	PP-ALLE + PP-Admin
Standard-Group - every user MUST be assigned to this group!	Management-Group - users who are added to this group receive additional menu items for the evaluation of company employees - Accounts evaluation ¹ , Calendar overview ² , Yearly calendar ³ und Statistics ⁴ .	Administrator-Group -Users added to this group get additional menu items for managing the Organigramms ⁵ , People ⁶ , Group and Roles ⁸ , as well as the ability to Switch users ⁹ to view the Personalwolke from the perspective of the selected user.

Of course it is also possible to add a user to all loose groups and thus unlock the administration AND management menu items to the user or a simple standard user is created which is only added to the loose group PP-ALLE.

WARNUNG

The menu item Time management --> Correction client represents a special case. Only persons who have assigned the Personnel role can use this correction client (regardless of the loose groups to which they have been added) to change bookings. In some cases users can also use correction client for tracking time.

Personalwolke Travel

If you are a user of the "Travel" module, the following loose groups are also available for managing user rights:

PP-TM-User	PP-TM-Manager	PP-TM-Admin
 Apply for / account for trip (depending on the definition according to the furnishing workshop) Info / My travels 	Management / Travel of my employees	 Administration / Travel Expenses / All Trips Management / Travel of my employees

Personalwolke Project-Time

If you are a user of the "Project Time" module, the following loose groups are also available for managing user rights:

PP-PTM-Usr	PP-PTM-Mgm	PP-PTM-ProjMngr	PP-PTM-Admin
 Project time booking Enter project time Info / My project times 	 Enter project time Management / project times of my employees 	 Management / Project expenses 	 Enter project time Administration / Project time / Projects Management / project times of my employees

How to add user to a group

We select the **PP-ALLE** group and click Save. This assigns the employee to the loose group **PP-ALLE**.

ttings Groups Roles Action	Permissions In competence of roleholders	Cache Login Attempts	NFC Tags Modules				
ose Gruppen PP ~							
	with Hist	tory 🗌					
New group				Valid from	Val	lid till	
New group Select an Option				Valid from	Va	lid till	l
Select an Option	Name		Valid from	×			l
	Name	ioskAdmin)	Valid from 28/01/2020	v V	۵		
Select an Option Orgstructure Solution Lose Gruppen PP				* V.	alid till	D	
Select an Option	🔮 PP-KioskAdmin (PP-Ki	histratoren)	28/01/2020	* V	alid till 1/01/3000	D m	

In summary, it can be said that when creating a new person regarding the groups / roles, the following things must be considered:

- Person has to be assigned to exactly one hierarchical group.
- Person has to be assigned to the loose group PP-ALLE.
- Person gets optional additional rights by adding to loose groups
 - PP management and / or PP admin (when using the time module)
 - PP-TM user / PP-TM manager / PP-TM admin (when using the travel module)
 - PP-PTM-User / PP-PTM-Mgm / PP-PTM-ProjMngr / PP-PTM-Admin (when using the project time module)
- Person gets optional additional rights (correction client) by adding the role Personnel

Role assignment for managers and personnel is explained in the next section.

Tab: Roles

Under **Roles**, you can find an overview of the roles assigned to this person in the company. The following screenshot shows that the person has some roles assigned.

Settings Groups Ro	les Action Permissions In compet	ence of roleholder	rs Cache	Login A	ttempts	NFC Tags	Modules	
		with	History 🗌					
+ New Role Assign	ment							
								Entries 1 - 3 of 3 \mid \ll \langle 1 \checkmark \rangle \gg Lines: 5
Name	Competence target	inherited from	Valid from		Valid till		Ranking	Delete / Edit
Personal	PersonalWolke Prof		10/06/2013	10	01/01/30	00 11	1	
and a second second second	*		19/01/2016		01/01/30	00 11	1	8 🖌
& Vorgesetzter	PP-GF (Personalwolke GmbH)							

If the employee is now to be assigned another role (superior, personnel), this is done by clicking on the **New Role Holder** button.

ings Groups	Roles	Action Permissions	In competence of roleholders	Cache L	ogin Attempts NFC Ta	igs Modules				
			with Hist	ory 🗌						
Vew Role Assign	nent									c
New Roleholder			Competence target		Valid from		Valid till		Ranking	
				~				0	1	

- New role assignment Selection of the role through clicking on the 3 horizontal dots (manager (Vorgesetzter), personnel (Personal) to be assigned to the employee.
- Competence target refers to the person/group for which the employee is to be responsible.
- Valid from / Valid to describes the period in which the employee is assigned the selected role.
- The **order** determines the deputy (sequence 1 = superior, 2 = deputy, 3,4 = if several persons are defined as deputies, the system determines who receives an application for processing).

Example: New role assignment "Vorgesetzter", competence objective: group, "PB-ENTW (development)" - this means that the person performs the role of superior for the group PB-ENTW, i.e. all applications submitted by a person from the group PB-ENTW and requiring approval / review by the role of superior end up with this person. Of course, a special person could also be appointed instead of the group. In this case, the Superior role only applies to the person who was defined.

A person can be assigned several roles with different competence goals!

ngs G	roups	Roles	Action Permissions	In compet	ence of roleholders	Cache	Login Attempts	NFC Tags	Modules			
					with His	tory 🗌						
v Role	Assignm	ent										
	Assignm holder	ent		Cor	npetence target		Valid from			Valid till	Ranking	

The assigned roles can also be withdrawn / changed from the user by means of Delete (Bin Symbol)/ Edit (Edit Symbol).

- 1. /daisy/personalwolke-default/6024-dsy.html?language=4
- $2. \quad / daisy/personal wolke-default/6025-dsy.html?language=4$
- 3. /daisy/personalwolke-default/6026-dsy.html?language=4
- 4. /daisy/personalwolke-default/6027-dsy.html?language=4
- 5. /daisy/personalwolke-default/5881-dsy.html?language=4

- 6. /daisy/personalwolke-default/5885-dsy.html?language=4
- $7. \quad / daisy/personal wolke-default/5884-dsy.html?language{=}4$
- $8. \quad / daisy/personal wolke-default/5886-dsy.html?language=4$
- 9. /daisy/personalwolke-default/5887-dsy.html?language=4